



FORTEST

Testing Technology. Together.

Data Manager v.1.5.5 for M-Series and T-Series ForTest




FORTEST

Testing Technology. Together.

Datamanager is a software application for Windows OS (XP,7,8,10) that can automatically download test results of ForTest equipment M-Series and T-Series

It run in background and at the start inicializa an RS232 connection (or a TCP/IP connection if the equipment mount the ethernet card) with a connected ForTest device





FORTEST

Testing Technology. Together.

From the option menu is it possible to configure the connection

The screenshot shows a 'Connection' dialog box with three tabs: 'Connection', 'Save settings', and 'Language'. The 'Connection' tab is active. Inside the dialog, there is a 'Serial Port' section with two fields: 'Serial Port:' with a dropdown menu showing 'COM32' and a small downward arrow, and 'Baud Rate [bps]:' with a text box containing '115200'. At the bottom right of the dialog are 'OK' and 'Cancel' buttons.



FORTEST

Testing Technology. Together.

And the file save format (Excel, Access, CSV)

The screenshot shows the 'Save settings' tab of a dialog box. It contains three main sections: 'File format' with three radio button options (Microsoft Access 97-2003 (*.mdb) is selected), 'Save Results' with three checked checkboxes (Good results, Bad results, Abort results), and 'Destination' with a text field for the path 'D:\PROGETTI .NET\DATA MANAGER 1.5\LTM1.4-SERIALE' and a 'Browse...' button. At the bottom, there is an 'Automatic save' section with a checked checkbox labeled 'Enable/Disable'. The dialog box has 'OK' and 'Cancel' buttons at the bottom right.

Connection Save settings Language

File format

- ☒ Microsoft Access 97-2003 (*.mdb)
- ☐ Microsoft Excel 97-2003 (*.xls)
- ☐ Comma Separated Values (*.csv)

Save Results

- ☒ Good results
- ☒ Bad results
- ☒ Abort results

Destination

Path D:\PROGETTI .NET\DATA MANAGER 1.5\LTM1.4-SERIALE Browse...

Automatic save

- ☒ Enable/Disable

OK Cancel



FORTEST

Testing Technology. Together.

After the end of a test results are automatically stored into the selected file format (for example Excel)

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	
1	Operator	C Barcode	Date	Hour	Program	N Filling Pre	Max Deca	Time Sett	Test Time	Pressure	F Decay	Ev	Time Pha	Phase	Result	
2			02/05/2018	15:27:53	0	1000	50000	20	5	0	0	8,59	Filling	Abort		
3			02/05/2018	15:28:06	0	1000	50000	20	5	56,81	0	0	Filling	Pressure under level		
4																
5																
6																
7																
8																
9																
10																
11																



Tutte le tabelle
Dispositivo01
Dispositivo01 : Tabella
Dispositivo02
Dispositivo02 : Tabella
Dispositivo03
Dispositivo03 : Tabella
Dispositivo04
Dispositivo04 : Tabella
Dispositivo05
Dispositivo05 : Tabella
Dispositivo06
Dispositivo06 : Tabella
Dispositivo07
Dispositivo07 : Tabella
Dispositivo08
Dispositivo08 : Tabella
Dispositivo09
Dispositivo09 : Tabella
Dispositivo10
Dispositivo10 : Tabella

OperatorCo	Barcode	TestDate	Hour	ProgramN	pFill	maxDecay	TSettling	testTimeSet	pFillEvaluat	decayEvaluat	timePhaseE
*		11/12/2017	13:35:27	0	3000	1	300	60	-10,7	0	0